



Cím: 1117 Budapest, Pázmány Péter sétány 1/A, 6. emelet 6.127 szoba
1088 Budapest, Múzeum körút 4/C, Alagsor 61/A. szoba

Telefon: 372-2500/6800

Fax: 372-2500/6741, 372-2991


E-mail: operator@elte.hu

Honlap: iig.elte.hu

How To Set Your Network Connection

You can use this How To if you use Microsoft Windows XP, but the settings also similar in other operating systems. You need Windows XP Service Pack 3 to use our Wi-Fi network.

In the Network's properties select "Wireless Networks". Here choose ELTE and click the Properties button.





Cím: 1117 Budapest, Pázmány Péter sétány 1/A, 6. emelet 6.127 szoba
1088 Budapest, Múzeum körút 4/C, Alagsor 61/A. szoba


Telefon: 372-2500/6800

Fax: 372-2500/6741, 372-2991

E-mail: operator@elte.hu

Honlap: iig.elte.hu

In the appearing dialog choose the "Association" tab. There set the "Network Authentication" to WPA2 and the "Data Encryption" to AES.





Cím: 1117 Budapest, Pázmány Péter sétány 1/A, 6. emelet 6.127 szoba
1088 Budapest, Múzeum körút 4/C, Alagsor 61/A. szoba

Telefon: 372-2500/6800


Fax: 372-2500/6741, 372-2991

E-mail: operator@elte.hu

Honlap: iig.elte.hu

Now select the "Authentication" tab. Here set the "EAP type" to "Protected EAP (PEAP)", and deselect the "Authenticate as computer..." and the "Authenticate as guest..." property.

Click the "Property" button.





Cím: 1117 Budapest, Pázmány Péter sétány 1/A, 6. emelet 6.127 szoba
1088 Budapest, Múzeum körút 4/C, Alagsor 61/A. szoba

Telefon: 372-2500/6800

Fax: 372-2500/6741, 372-2991


E-mail: operator@elte.hu

Honlap: iig.elte.hu

Firstly mark the "Validate server certificate" option .

Secondly find and mark the " DigiCert Assured ID Root CA " what you can find in the "Trusted Root Certification Authorities" list.

Thirdly set the "Select Authentication Method" to "Secured password (EAP-MSCHAP v2) ". After that click the "Configure..." button.





Cím: 1117 Budapest, Pázmány Péter sétány 1/A, 6. emelet 6.127 szoba
1088 Budapest, Múzeum körút 4/C, Alagsor 61/A. szoba

Telefon: 372-2500/6800


Fax: 372-2500/6741, 372-2991

E-mail: operator@elte.hu

Honlap: iig.elte.hu

Deselect the "Automatically use my Windows logon name and password (and domain if any)."

Finally click OK to any open dialog boxes.



If you make these settings you can connect to the ELTE's wireless network. After connecting you must type your username and password. At first connection maybe you must accept ELTE's authentication certification.